

Setup bleibt hängen. Jemand ne Idee?

Beitrag von „5T33Z0“ vom 31. Oktober 2020, 13:48

[Hitchi](#) Die Config wurde im Zuge des Updates auf OpenCore 0.6.2 nicht aktualisiert:

```
#####  
# OC Config Compare #  
#####
```

Checking for values missing from User plist:

config.plist -> DeviceProperties -> Add - Missing Key: PciRoot(0x0)/Pci(0x1b,0x0)

config.plist -> Kernel -> Emulate - Missing Key: DummyPowerManagement

config.plist -> Kernel -> Emulate - Missing Key: MaxKernel

config.plist -> Kernel -> Emulate - Missing Key: MinKernel

config.plist -> Kernel -> Quirks - Missing Key: ExtendBTFeatureFlags

config.plist -> Kernel -> Quirks - Missing Key: LegacyCommpage

config.plist -> NVRAM -> Add -> 7C436110-AB2A-4BBB-A880-FE41995C9F82 - Missing Key: prev-lang:kbd

config.plist -> PlatformInfo -> Generic - Missing Key: SystemMemoryStatus

config.plist -> PlatformInfo -> Generic - Missing Key: ProcessorType

Checking for values missing from Sample:

Sample.plist -> DeviceProperties -> Add - Missing Key: PciRoot(0x0)/Pci(0x1f,0x03) (ignorieren)

Sample.plist -> DeviceProperties -> Add - Missing Key: PciRoot(0x0)/Pci(0x2,0x0)

Sample.plist -> Kernel -> Quirks - Missing Key: DummyPowerManagement

Sample.plist -> NVRAM -> Add -> 4D1EDE05-38C7-4A6A-9CC6-4BCCA8B38C14 - Missing Key: run-efi-updatery

Sample.plist -> NVRAM -> Add -> 4D1FDA02-38C7-4A6A-9CC6-4BCCA8B30102 - Missing Key: run-efi-updater

Sample.plist -> PlatformInfo - Missing Key: SMBIOS

Press [enter] to return...

Dringend: in Deiner config den Eintrag **Kernel -> Quirks > DummyPowerManagement** nach **Kernel -> Emulate > DummyPowerManagement** verschieben.

Die restlichen **grünen Einträge** aus sample.plist von 062 in config kopieren.

Dann speichern und nochmal probieren.

PS: Da sind unmengen an überflüssigen von Treibern und Tools drin übrigens. Du brauchst aber nur:

- AudioDxe.efi, HfsPlus.efi, OpenRuntime.efi, OpenCanopy.efi,(nur für Optik).

Tools brauchst du gar nichts von bis auf OpenShell evtl.

Den ganzen ballast rauswerfen, neuen Snapshot der config mit ProperTree erstellen und dann neustarten.