

Erledigt

Ozmosis + El Capitan

Beitrag von „al6042“ vom 20. Oktober 2015, 22:08

BTW:

I had problems with using the nvram command to set the csr-active-config, so I put it directly into my defaults.plist on /EFI/Oz.

Code

1. `<key>Defaults:7C436110-AB2A-4BBB-A880-FE41995C9F82</key>`
2. `<dict>`
3. `<key>boot-args</key>`
4. `<string>darkwake=8</string>`
5. `<key>csr-active-config</key>`
6. `<string>67000000</string>`

Since it is a string you don't have to use the %-sign in between.
To check if the setting is used, you can use the terminal command

Code

1. `nvram -p`

which should give you the following line back:

Code

1. `csr-active-config g%00%00%00`

This matches the same entry as you would have while using Clover with

Code

1. <key>RtVariables</key>
2. <dict>
3. <key>BooterConfig</key>
4. <string>0x28</string>
5. <key>CsrActiveConfig</key>
6. <string>0x67</string>