

M720Q BIOS Config

- USB Setup
 - USB Support - Enabled
 - USB Legacy Support - Enabled
 - USB Enumeration Delay - Disabled
 - Front USB Ports , Rear USB Ports - Everything Enabled
- ATA Drive Setup
 - SATA Controller - Enabled
 - SATA Drive 1 - Enabled
 - Configure SATA as - AHCI
 - Hard-disk Pre Delay - Disabled
- Video Setup
 - Select Active Video - Auto
- PCI Express Configuration
 - ASPM Support - Disabled
 - PCIe 8x Slot Speed - Auto
- Network Setup
 - Onboard Ethernet Controller - Enabled
 - PXE Option ROM, PXE IPv4 , PXE IPv6 - Disabled
- Audio Setup
 - Onboard Audio Controller -> Internal Speaker - Enabled
- Intel (R) Manageability (Cannot be edited)
 - ME Firmware Version 12.0.35.1427
 - Manageability Type - None
- Intel (R) Software Guard Extensions
 - Intel(R) SGX Control - Software Controller
 - Current State : Disabled
- Intel (R) SIPP Support - Enabled
- Dust Shield Alert - Disabled
- Security
 - Device Guard - Disabled
 - Chassis Intrusion Detection - Disabled
 - Configuration Change Detection - Disabled
 - Password Count Exceeded Error - Enabled
 - Computrace
 - ◆ Current Setting - Enabled
 - ◆ Current State - Not Activated
 - Secure Boot - Disabled
 - Network Office Locker - Disabled
 - TGC Feature Setup
 - ◆ TCG Security Device - Discrete TPM
 - ◆ Security Chip 2.0 - Enabled
 - ◆ Clear TCG Security Feature - No

-
- Startup
 - CSM - Disabled
 - Boot Mode - UEFI Only
- CPU Setup
 - EIST Support - Enabled
 - Intel HT - Enabled
 - Core Multi Processing - Enabled
 - Intel Virtualization - Enabled
 - VT-d - Enabled
 - TxT - Disabled
 - C1E Support - Enabled
 - Turbo Mode - Enabled
- Power
 - After Power Loss - Last State
 - Enhanced Power Saving Mode - Disabled
 - Smart Power On - Disabled
 - Intelligent Cooling Engine
 - ◆ ICE Performance Mode - Better Acoustic Performance
 - ◆ ICE Thermal Alert - Enabled
 - Automatic Power On
 - ◆ Wake on Lan - Disabled
 - ◆ Wake from Serial - Disabled
 - ◆ Wake on Alarm - Disabled