

Erledigt

Tool um Ozmosis-Parameter auszulesen/manipulieren

Beitrag von „al6042“ vom 29. Februar 2016, 22:18

Nope...

der %00 heisst NO, während der %01 YES lautet:

▼ Defaults:1F8E0C02-58A9-4E34-AE22-2B63745FA101	Dictionary	9 key/value pairs
AAPL,ig-platform-id	Number	⌘ 220.332.035
BootEntryTemplate	String	⌘ \$label
DarwinDiskTemplate	String	⌘ \$label
DarwinRecoveryDiskTemplate	String	⌘ \$label
DisableBootEntriesFilter	Boolean	⌘ YES
DisableIntelInjection	Boolean	⌘ NO
DisableNvidiaInjection	Boolean	⌘ YES
TimeOut	Number	⌘ 5
UserInterface	Boolean	⌘ YES

Code

1. <key>Defaults:1F8E0C02-58A9-4E34-AE22-2B63745FA101</key>
2. <dict>
3. <key>AAPL,ig-platform-id</key>
4. <integer>220332035</integer>
5. <key>BootEntryTemplate</key>
6. <string>\$label</string>
7. <key>DarwinDiskTemplate</key>
8. <string>\$label</string>
9. <key>DarwinRecoveryDiskTemplate</key>
10. <string>\$label</string>
11. <key>DisableBootEntriesFilter</key>
12. <true/>
13. <key>DisableIntelInjection</key>
14. <false/>
15. <key>DisableNvidiaInjection</key>
16. <true/>
17. <key>TimeOut</key>
18. <integer>5</integer>
19. <key>UserInterface</key>
20. <true/>
21. </dict>

Alles anzeigen

Code

1. Al6042-iMac:~ al6042\$ nvram 1F8E0C02-58A9-4E34-AE22-2B63745FA101:DisableBootEntriesFilter
2. 1F8E0C02-58A9-4E34-AE22-2B63745FA101:DisableBootEntriesFilter %01
3. Al6042-iMac:~ al6042\$ nvram 1F8E0C02-58A9-4E34-AE22-2B63745FA101:DisableIntelInjection
4. 1F8E0C02-58A9-4E34-AE22-2B63745FA101:DisableIntelInjection %00
5. Al6042-iMac:~ al6042\$ nvram 1F8E0C02-58A9-4E34-AE22-2B63745FA101:DisableNvidiaInjection
6. 1F8E0C02-58A9-4E34-AE22-2B63745FA101:DisableNvidiaInjection %01
7. Al6042-iMac:~ al6042\$ nvram 1F8E0C02-58A9-4E34-AE22-2B63745FA101:UserInterface
8. 1F8E0C02-58A9-4E34-AE22-2B63745FA101:UserInterface %01